

15-213

Integer Representations Jan. 23, 2001

Topics

- **Numeric Encodings**
 - Unsigned & Two's complement
- **Programming Implications**
 - C promotion rules

class03.ppt

CS 213 S'01

Notation

W: Number of Bits in "Word"

C Data Type	Typical 32-bit	Alpha
long int	32	64
int	32	32
short	16	16
char	8	8

Integers

- Lower case
- E.g., x, y, z

Bit Vectors

- Upper Case
- E.g., X, Y, Z
- Write individual bits as integers with value 0 or 1
- E.g., $X = x_{w-1}, x_{w-2}, \dots, x_0$
 - Most significant bit on left

class03.ppt

- 2 -

CS 213 S'01

Encoding Integers

Unsigned

$$B2U(X) = \sum_{i=0}^{w-1} x_i \cdot 2^i$$

Two's Complement

$$B2T(X) = -x_{w-1} \cdot 2^{w-1} + \sum_{i=0}^{w-2} x_i \cdot 2^i$$

```
short int x = 15213;
short int y = -15213;
```

Sign Bit

- C short 2 bytes long

	Decimal	Hex	Binary
x	15213	3B 6D	00111011 01101101
y	-15213	C4 93	11000100 10010011

Sign Bit

- For 2's complement, most significant bit indicates sign
 - 0 for nonnegative
 - 1 for negative

class03.ppt

- 3 -

CS 213 S'01

Encoding Example (Cont.)

```
x = 15213: 00111011 01101101
y = -15213: 11000100 10010011
```

Weight	15213	-15213
1	1	1
2	0	0
4	1	4
8	1	8
16	0	0
32	1	32
64	1	64
128	0	0
256	1	256
512	1	512
1024	0	0
2048	1	2048
4096	1	4096
8192	1	8192
16384	0	0
-32768	0	0
Sum	15213	-15213

class03.ppt

- 4 -

CS 213 S'01

Other Encoding Schemes

Other less common encodings

- One's complement: Invert bits for negative numbers
- Sign magnitude: Invert sign bit for negative numbers

short int

15213	Unsigned	00111011 01101101
-15213	Two's complement	11000100 10010011
-15213	One's complement	11000100 10010010
-15213	Sign magnitude	10111011 01101101

ISO C does not define what encoding machines use for signed integers, but 95% (or more) use two's complement.

For truly portable code, don't count on it.

class03.ppt

- 5 -

CS 213 S'01

Numeric Ranges

Unsigned Values

- $UMin = 0$
000...0
- $UMax = 2^w - 1$
111...1

Two's Complement Values

- $TMin = -2^{w-1}$
100...0
- $TMax = 2^{w-1} - 1$
011...1

Other Values

- Minus 1
111...1

Values for $W = 16$

	Decimal	Hex	Binary
UMax	65535	FF FF	11111111 11111111
TMax	32767	7F FF	01111111 11111111
TMin	-32768	80 00	10000000 00000000
-1	-1	FF FF	11111111 11111111
0	0	00 00	00000000 00000000

class03.ppt

- 6 -

CS 213 S'01

Values for Different Word Sizes

	W			
	8	16	32	64
UMax	255	65,535	4,294,967,295	18,446,744,073,709,551,615
TMax	127	32,767	2,147,483,647	9,223,372,036,854,775,807
TMin	-128	-32,768	-2,147,483,648	-9,223,372,036,854,775,808

Observations

- $|TMin| = TMax + 1$
– Asymmetric range
- $UMax = 2 * TMax + 1$

C Programming

- `#include <limits.h>`
– Harbison and Steele, 5.1
- Declares constants, e.g.,
– `ULONG_MAX`
– `LONG_MAX`
– `LONG_MIN`
- Values platform-specific

class03.ppt

- 7 -

CS 213 S'01

Unsigned & Signed Numeric Values

X	B2U(X)	B2T(X)
0000	0	0
0001	1	1
0010	2	2
0011	3	3
0100	4	4
0101	5	5
0110	6	6
0111	7	7
1000	8	-8
1001	9	-7
1010	10	-6
1011	11	-5
1100	12	-4
1101	13	-3
1110	14	-2
1111	15	-1

Example Values

- $W = 4$

Equivalence

- Same encodings for nonnegative values

Uniqueness

- Every bit pattern represents unique integer value
- Each representable integer has unique bit encoding

⇒ Can Invert Mappings

- $U2B(x) = B2U^{-1}(x)$
– Bit pattern for unsigned integer
- $T2B(x) = B2T^{-1}(x)$
– Bit pattern for two's comp integer

class03.ppt

- 8 -

CS 213 S'01

Casting Signed to Unsigned

C Allows Conversions from Signed to Unsigned

```
short int      x = 15213;
unsigned short int ux = (unsigned short) x;
short int      y = -15213;
unsigned short int uy = (unsigned short) y;
```

Resulting Value


- No change in bit representation
- Nonnegative values unchanged
- $ux = 15213$
- Negative values change into (large) positive values
- $uy = 50323$

class03.ppt

- 9 -

CS 213 S'01

Relation Between 2's Comp. & Unsigned



$$ux = \begin{matrix} w-1 & & & & 0 \\ \boxed{+} & \boxed{+} & \boxed{+} & \dots & \boxed{+} & \boxed{+} & \boxed{+} \\ -x & \boxed{-} & \boxed{+} & \dots & \boxed{+} & \boxed{+} & \boxed{+} \end{matrix}$$

$$+2^{w-1} - 2^{w-1} = 2 * 2^{w-1} = 2^w$$

$$ux = \begin{cases} x & x \geq 0 \\ x + 2^w & x < 0 \end{cases}$$

class03.ppt

- 10 -

CS 213 S'01

Relation Between Signed & Unsigned

Weight	-15213		50323	
1	1	1	1	1
2	1	2	1	2
4	0	0	0	0
8	0	0	0	0
16	1	16	1	16
32	0	0	0	0
64	0	0	0	0
128	1	128	1	128
256	0	0	0	0
512	0	0	0	0
1024	1	1024	1	1024
2048	0	0	0	0
4096	0	0	0	0
8192	0	0	0	0
16384	1	16384	1	16384
32768	1	-32768	1	32768
Sum		-15213		50323

• $uy = y + 2 * 32768 = y + 65536$

class03.ppt

- 11 -

CS 213 S'01

From Two's Complement to Unsigned


• $T2U(x)$
= $B2U(T2B(x))$
= $x + x_{w-1} 2^w$

• What you get in C:

```
unsigned t2u(int x)
{
    return (unsigned) x;
}
```

X	B2U(X)	B2T(X)
1010	10	-6

← +16



class03.ppt

- 12 -

CS 213 S'01


From Unsigned to Two's Complement

$$\begin{aligned} \text{U2T}(x) &= \text{B2T}(\text{U2B}(x)) \\ &= x - x_{n-1} 2^n \end{aligned}$$

What you get in C:

```
int u2t(unsigned x)
{
    return (int) x;
}
```

X	B2U(X)	B2T(X)
1010	10	-6



class03.ppt

- 13 -

CS 213 S'01

Signed vs. Unsigned in C

Constants

- By default are considered to be signed integers
- Unsigned if have "U" as suffix
0U, 4294967259U

Casting

- Explicit casting between signed & unsigned same as U2T and T2U
- ```
int tx, ty;
unsigned ux, uy;
tx = (int) ux;
uy = (unsigned) ty;
```
- Implicit casting also occurs via assignments and procedure calls
- ```
tx = ux;
uy = ty;
```

class03.ppt

- 14 -

CS 213 S'01

Casting Surprises

Expression Evaluation

- If mix unsigned and signed in single expression, signed values implicitly cast to unsigned
- Including comparison operations <, >, ==, <=, >=
- Examples for W = 32

Constant ₁	Constant ₂	Relation	Evaluation
0	0U	==	unsigned
-1	0	<	signed
-1	0U	>	unsigned
2147483647	-2147483648	>	signed
2147483647U	-2147483648	<	unsigned
-1	-2	>	signed
(unsigned) -1	-2	>	unsigned
2147483647	2147483648U	<	unsigned
2147483647	(int) 2147483648U	>	signed

class03.ppt


- 15 -

CS 213 S'01

Explanation of Casting Surprises

2's Comp. → Unsigned

- Ordering Inversion
- Negative → Big Positive



class03.ppt

- 16 -

CS 213 S'01

Sign Extension


Task:

- Given w -bit signed integer x
- Convert it to $w+k$ -bit integer with same value

Rule:

- Make k copies of sign bit:

- $X' = \underbrace{X_{w-1}, \dots, X_{w-1}}_{k \text{ copies of MSB}}, X_{w-1}, X_{w-2}, \dots, X_0$



class03.ppt

- 17 -

CS 213 S'01

Sign Extension Example

```
short int x = 15213;
int      ix = (int) x;
short int y = -15213;
int      iy = (int) y;
```

	Decimal	Hex	Binary
x	15213	3B 6D	00111011 01101101
ix	15213	00 00 C4 92	00000000 00000000 00111011 01101101
y	-15213	C4 93	11000100 10010011
iy	-15213	FF FF C4 93	11111111 11111111 11000100 10010011

- Converting from smaller to larger integer data type
- C automatically performs sign extension

class03.ppt


- 18 -

CS 213 S'01

Justification For Sign Extension

Prove Correctness by Induction on k

- Induction Step: extending by single bit maintains value



- Key observation: $-2^{w-1} = -2^w + 2^{w-1}$

- Look at weight of upper bits:

$$X \quad -2^{w-1} X_{w-1}$$

$$X' \quad -2^w X_{w-1} + 2^{w-1} X_{w-1} = -2^{w-1} X_{w-1}$$


class03.ppt

- 19 -

CS 213 S'01

Casting Order Dependencies

```
short int x = 15213;
short int y = -15213;
unsigned iux = (unsigned)(unsigned short) x;
unsigned iuy = (unsigned)(unsigned short) y;
unsigned uix = (unsigned) (int) x;
unsigned uiy = (unsigned) (int) y;
unsigned uuy = y;
```



```
iux = 15213: 00000000 00000000 00111011 01101101
iuy = 50323: 00000000 00000000 11000100 10010011
uix = 15213: 00000000 00000000 00111011 01101101
uiy = 4294952083: 11111111 11111111 11000100 10010011
uuy = 4294952083: 11111111 11111111 11000100 10010011
```

class03.ppt

- 20 -

CS 213 S'01

Why Should I Use Unsigned?

Don't Use Just Because Number is Never Negative

- C compiler on Alpha generates less efficient code
 - Comparable code on Intel/Linux

```
unsigned i;  
for (i = 1; i < cnt; i++)  
    a[i] += a[i-1];
```

- Easy to make mistakes

```
for (i = cnt-2; i >= 0; i--)  
    a[i] += a[i+1];
```

Do Use When Performing Modular Arithmetic

- Multiprecision arithmetic
- Other esoteric stuff

Do Use When Need Extra Bit's Worth of Range

- Working right up to limit of word size