

# **15-213**

## **Machine-Level Programming I: Introduction January 29, 2002**

### **Topics**

- **Assembly Programmer's Execution Model**
- **Accessing Information**
  - Registers
  - Memory
- **Arithmetic operations**

# IA32 Processors

**Totally Dominate Computer Market**

## **Evolutionary Design**

- Starting in 1978 with 8086
- Added more features as time goes on
- Still support old features, although obsolete

## **Complex Instruction Set Computer (CISC)**

- Many different instructions with many different formats
  - But, only small subset encountered with Linux programs
- Hard to match performance of Reduced Instruction Set Computers (RISC)
- But, Intel has done just that!

# X86 Evolution: Programmer's View

Name	Date	Transistors
------	------	-------------

<b>8086</b>	<b>1978</b>	<b>29K</b>
-------------	-------------	------------

- 16-bit processor. Basis for IBM PC & DOS
- Limited to 1MB address space. DOS only gives you 640K

<b>80286</b>	<b>1982</b>	<b>134K</b>
--------------	-------------	-------------

- Added elaborate, but not very useful, addressing scheme
- Basis for IBM PC-AT and Windows

<b>386</b>	<b>1985</b>	<b>275K</b>
------------	-------------	-------------

- Extended to 32 bits. Added “flat addressing”
- Capable of running Unix
- Linux/gcc uses no instructions introduced in later models

<b>486</b>	<b>1989</b>	<b>1.9M</b>
------------	-------------	-------------

<b>Pentium</b>	<b>1993</b>	<b>3.1M</b>
----------------	-------------	-------------

# X86 Evolution: Programmer's View

Name	Date	Transistors
------	------	-------------

<b>Pentium/MMX</b>	<b>1997</b>	<b>4.5M</b>
--------------------	-------------	-------------

- Added special collection of instructions for operating on 64-bit vectors of 1, 2, or 4 byte integer data

<b>PentiumPro</b>	<b>1995</b>	<b>6.5M</b>
-------------------	-------------	-------------

- Added conditional move instructions
- Big change in underlying microarchitecture

<b>Pentium III</b>	<b>1999</b>	<b>8.2M</b>
--------------------	-------------	-------------

- Added “streaming SIMD” instructions for operating on 128-bit vectors of 1, 2, or 4 byte integer or floating point data
- Our fish machines

<b>Pentium 4</b>	<b>2001</b>	<b>42M</b>
------------------	-------------	------------

- Added 8-byte formats and 144 new instructions for streaming SIMD mode

# X86 Evolution: Clones

## Advanced Micro Devices (AMD)

- **Historically**
  - AMD has followed just behind Intel
  - A little bit slower, a lot cheaper
- **Recently**
  - Recruited top circuit designers from Digital Equipment Corp.
  - Exploited fact that Intel distracted by IA64
  - Now are close competitors to Intel
- **Developing own extension to 64-bits**

## Transmeta

- **Recent start-up**
  - Employer of Linus Torvalds
- **Radically different approach to implementation**
  - Translates x86 code into “Very Long Instruction Word” (VLIW) code
  - High degree of parallelism
- **Shooting for low-power market**


# New Species: IA64

Name	Date	Transistors
------	------	-------------

<b>Itanium</b>	<b>2001</b>	<b>10M</b>
----------------	-------------	------------

- Extends to IA64, a 64-bit architecture
- Radically new instruction set designed for high performance
- Will be able to run existing IA32 programs
  - On-board “x86 engine”
- Joint project with Hewlett-Packard

# Assembly Programmer's View




## Programmer-Visible State

- **EIP      Program Counter**
  - Address of next instruction
- **Register File**
  - Heavily used program data
- **Condition Codes**
  - Store status information about most recent arithmetic operation
  - Used for conditional branching

- **Memory**
  - Byte addressable array
  - Code, user data, (some) OS data
  - Includes stack used to support procedures

# Turning C into Object Code

- Code in files `p1.c p2.c`
- Compile with command: `gcc -O p1.c p2.c -o p`
  - Use optimizations (`-O`)
  - Put resulting binary in file `p`





# Compiling Into Assembly

## C Code

```
int sum(int x, int y)
{
    int t = x+y;
    return t;
}
```

## Generated Assembly

```
_sum:
    pushl %ebp
    movl %esp,%ebp
    movl 12(%ebp),%eax
    addl 8(%ebp),%eax
    movl %ebp,%esp
    popl %ebp
    ret
```

Obtain with command

```
gcc -O -S code.c
```

Produces file `code.s`

# Assembly Characteristics

## Minimal Data Types

- **“Integer” data of 1, 2, or 4 bytes**
  - Data values
  - Addresses (untyped pointers)
- **Floating point data of 4, 8, or 10 bytes**
- **No aggregate types such as arrays or structures**
  - Just contiguously allocated bytes in memory

## Primitive Operations

- **Perform arithmetic function on register or memory data**
- **Transfer data between memory and register**
  - Load data from memory into register
  - Store register data into memory
- **Transfer control**
  - Unconditional jumps to/from procedures
  - Conditional branches

# Object Code

## Code for `sum`

`0x401040 <sum>:`

`0x55`

`0x89`

`0xe5`

`0x8b`

`0x45`

`0x0c`

`0x03`

`0x45`

`0x08`

`0x89`

`0xec`

`0x5d`

`0xc3`

- Total of 13 bytes
- Each instruction 1, 2, or 3 bytes
- Starts at address `0x401040`

## Assembler

- Translates `.s` into `.o`
- Binary encoding of each instruction
- Nearly-complete image of executable code
- Missing linkages between code in different files

## Linker

- Resolves references between files
- Combines with static run-time libraries
  - E.g., code for `malloc`, `printf`
- Some libraries are *dynamically linked*
  - Linking occurs when program begins execution

# Machine Instruction Example

## C Code

```
int t = x+y;
```

- Add two signed integers

## Assembly

```
addl 8(%ebp),%eax
```

**Similar to  
expression**

**x += y**

- Add 2 4-byte integers
  - “Long” words in GCC parlance
  - Same instruction whether signed or unsigned
- Operands:
  - x: Register      %eax
  - y: Memory      M[%ebp+8]
  - t: Register      %eax

» Return function value in %eax

```
0x401046:      03 45 08
```

## Object Code

- 3-byte instruction
- Stored at address 0x401046

# Disassembling Object Code

## Disassembled

```
00401040 <_sum>:
    0:      55          push    %ebp
    1:      89 e5      mov     %esp,%ebp
    3:      8b 45 0c   mov     0xc(%ebp),%eax
    6:      03 45 08   add     0x8(%ebp),%eax
    9:      89 ec      mov     %ebp,%esp
    b:      5d      pop     %ebp
    c:      c3      ret
    d:      8d 76 00  lea     0x0(%esi),%esi
```

## Disassembler

`objdump -d p`

- Useful tool for examining object code
- Analyzes bit pattern of series of instructions
- Produces approximate rendition of assembly code
- Can be run on either `a.out` (complete executable) or `.o` file

# Alternate Disassembly

## Disassembled

### Object

0x401040:

0x55

0x89

0xe5

0x8b

0x45

0x0c

0x03

0x45

0x08

0x89

0xec

0x5d

0xc3

0x401040	<sum>:	push	%ebp
0x401041	<sum+1>:	mov	%esp,%ebp
0x401043	<sum+3>:	mov	0xc(%ebp),%eax
0x401046	<sum+6>:	add	0x8(%ebp),%eax
0x401049	<sum+9>:	mov	%ebp,%esp
0x40104b	<sum+11>:	pop	%ebp
0x40104c	<sum+12>:	ret	
0x40104d	<sum+13>:	lea	0x0(%esi),%esi

### Within gdb Debugger

`gdb p`

`disassemble sum`

- Disassemble procedure

`x/13b sum`

- Examine the 13 bytes starting at `sum`

# What Can be Disassembled?

```
% objdump -d WINWORD.EXE
```

```
WINWORD.EXE:      file format pei-i386
```

```
No symbols in "WINWORD.EXE".
```

```
Disassembly of section .text:
```

```
30001000 <.text>:
```

```
30001000:  55                      push    %ebp
30001001:  8b ec                  mov     %esp,%ebp
30001003:  6a ff                  push    $0xffffffff
30001005:  68 90 10 00 30        push    $0x30001090
3000100a:  68 91 dc 4c 30        push    $0x304cdc91
```

- Anything that can be interpreted as executable code
- Disassembler examines bytes and reconstructs assembly source

# Moving Data

## Moving Data

`movl Source, Dest`: Move 4-byte (“long”) word

- Accounts for 31% of all instructions in sample

## Operand Types

- **Immediate: Constant integer data**
  - Like C constant, but prefixed with ‘\$’
  - E.g., \$0x400, \$-533
  - Encoded with 1, 2, or 4 bytes
- **Register: One of 8 integer registers**
  - But %esp and %ebp reserved for special use
  - Others have special uses for particular instructions
- **Memory: 4 consecutive bytes of memory**
  - Various “address modes”

%eax
%edx
%ecx
%ebx
%esi
%edi
%esp
%ebp



# movl Operand Combinations

	Source	Destination		C Analog
movl	Imm	Reg	movl \$0x4,%eax	temp = 0x4;
		Mem	movl \$-147,(%eax)	*p = -147;
	Reg	Reg	movl %eax,%edx	temp2 = temp1;
		Mem	movl %eax,(%edx)	*p = temp;
	Mem	Reg	movl (%eax),%edx	temp = *p;

- Cannot do memory-memory transfers with single instruction

# Simple Addressing Modes

**Normal (R) Mem[Reg[R]]**

- Register R specifies memory address

```
movl (%ecx), %eax
```

**Displacement D(R) Mem[Reg[R]+D]**

- Register R specifies start of memory region
- Constant displacement D specifies offset

```
movl 8(%ebp), %edx
```

# Using Simple Addressing Modes

```
void swap(int *xp, int *yp)
{
    int t0 = *xp;
    int t1 = *yp;
    *xp = t1;
    *yp = t0;
}
```

swap:

```
    pushl %ebp
    movl %esp,%ebp
    pushl %ebx
```

} Set Up

```
    movl 12(%ebp),%ecx
    movl 8(%ebp),%edx
    movl (%ecx),%eax
    movl (%edx),%ebx
    movl %eax, (%edx)
    movl %ebx, (%ecx)
```

} Body

```
    movl -4(%ebp),%ebx
    movl %ebp,%esp
    popl %ebp
    ret
```


} Finish

# Understanding Swap

```
void swap(int *xp, int *yp)
{
    int t0 = *xp;
    int t1 = *yp;
    *xp = t1;
    *yp = t0;
}
```

Register	Variable
%ecx	yp
%edx	xp
%eax	t1
%ebx	t0

```
movl 12(%ebp),%ecx # ecx = yp
movl 8(%ebp),%edx  # edx = xp
movl (%ecx),%eax   # eax = *yp (t1)
movl (%edx),%ebx   # ebx = *xp (t0)
movl %eax, (%edx)  # *xp = eax
movl %ebx, (%ecx)  # *yp = ebx
```



# Indexed Addressing Modes

## Most General Form

**$D(Rb, Ri, S)$                        $Mem[Reg[Rb] + S * Reg[Ri] + D]$**

- **D:**      Constant “displacement” 1, 2, or 4 bytes
- **Rb:**    Base register: Any of 8 integer registers
- **Ri:**    Index register: Any, except for `%esp`
  - Unlikely you’d use `%ebp`, either
- **S:**      Scale: 1, 2, 4, or 8

## Special Cases

<b><math>(Rb, Ri)</math></b>	<b><math>Mem[Reg[Rb] + Reg[Ri]]</math></b>
<b><math>D(Rb, Ri)</math></b>	<b><math>Mem[Reg[Rb] + Reg[Ri] + D]</math></b>
<b><math>(Rb, Ri, S)</math></b>	<b><math>Mem[Reg[Rb] + S * Reg[Ri]]</math></b>

# Address Computation Instruction

**`leal Src, Dest`**

- *Src* is address mode expression
- Set *Dest* to address denoted by expression

## Uses

- Computing address without doing memory reference
  - E.g., translation of `p = &x[i];`
- Computing arithmetic expressions of the form  $x + k \cdot y$ 
  - $k = 1, 2, 4, \text{ or } 8$ .

# Some Arithmetic Operations

## Format

## Computation

### Two Operand Instructions

<b><i>addl Src, Dest</i></b>	<b><i>Dest = Dest + Src</i></b>	
<b><i>subl Src, Dest</i></b>	<b><i>Dest = Dest - Src</i></b>	
<b><i>imull Src, Dest</i></b>	<b><i>Dest = Dest * Src</i></b>	
<b><i>sall Src, Dest</i></b>	<b><i>Dest = Dest &lt;&lt; Src</i></b>	Also called <b><i>shll</i></b>
<b><i>sarl Src, Dest</i></b>	<b><i>Dest = Dest &gt;&gt; Src</i></b>	Arithmetic
<b><i>shrl Src, Dest</i></b>	<b><i>Dest = Dest &gt;&gt; Src</i></b>	Logical
<b><i>xorl Src, Dest</i></b>	<b><i>Dest = Dest ^ Src</i></b>	
<b><i>andl Src, Dest</i></b>	<b><i>Dest = Dest &amp; Src</i></b>	
<b><i>orl Src, Dest</i></b>	<b><i>Dest = Dest   Src</i></b>	

### One Operand Instructions

<b><i>incl Dest</i></b>	<b><i>Dest = Dest + 1</i></b>
<b><i>decl Dest</i></b>	<b><i>Dest = Dest - 1</i></b>
<b><i>negl Dest</i></b>	<b><i>Dest = - Dest</i></b>
<b><i>notl Dest</i></b>	<b><i>Dest = ~ Dest</i></b>

# Using `leal` for Arithmetic Expressions

```
int arith
(int x, int y, int z)
{
    int t1 = x+y;
    int t2 = z+t1;
    int t3 = x+4;
    int t4 = y * 48;
    int t5 = t3 + t4;
    int rval = t2 * t5;
    return rval;
}
```

arith:

```
pushl %ebp
movl %esp,%ebp
```

} Set Up

```
movl 8(%ebp),%eax
movl 12(%ebp),%edx
leal (%edx,%eax),%ecx
leal (%edx,%edx,2),%edx
sall $4,%edx
addl 16(%ebp),%ecx
leal 4(%edx,%eax),%eax
imull %ecx,%eax
```

} Body


```
movl %ebp,%esp
popl %ebp
ret
```

} Finish



# Understanding arith

```
int arith
(int x, int y, int z)
{
    int t1 = x+y;
    int t2 = z+t1;
    int t3 = x+4;
    int t4 = y * 48;
    int t5 = t3 + t4;
    int rval = t2 * t5;
    return rval;
}
```



```
movl 8(%ebp),%eax      # eax = x
movl 12(%ebp),%edx     # edx = y
leal (%edx,%eax),%ecx  # ecx = x+y (t1)
leal (%edx,%edx,2),%edx # edx = 3*y
sall $4,%edx          # edx = 48*y (t4)
addl 16(%ebp),%ecx     # ecx = z+t1 (t2)
leal 4(%edx,%eax),%eax # eax = 4+t4+x (t5)
imull %ecx,%eax        # eax = t5*t2 (rval)
```

# Another Example

```
int logical(int x, int y)
{
    int t1 = x^y;
    int t2 = t1 >> 17;
    int mask = (1<<13) - 7;
    int rval = t2 & mask;
    return rval;
}
```

$2^{13} = 8192, 2^{13} - 7 = 8185$

logical:

```
pushl %ebp
movl %esp,%ebp
```

} Set Up

```
movl 8(%ebp),%eax
xorl 12(%ebp),%eax
sarl $17,%eax
andl $8185,%eax
```

} Body

```
movl %ebp,%esp
popl %ebp
ret
```

} Finish

```
movl 8(%ebp),%eax
xorl 12(%ebp),%eax
sarl $17,%eax
andl $8185,%eax
```

```
eax = x
eax = x^y      (t1)
eax = t1>>17  (t2)
eax = t2 & 8185
```

# CISC Properties

**Instruction can reference different operand types**

- Immediate, register, memory

**Arithmetic operations can read/write memory**

**Memory reference can involve complex computation**


- $Rb + S * Ri + D$
- Useful for arithmetic expressions, too

**Instructions can have varying lengths**

- IA32 instructions can range from 1 to 15 bytes

# Summary: Abstract Machines

## Machine Models




## Data

- 1) char
- 2) int, float
- 3) double
- 4) struct, array
- 5) pointer

## Control

- 1) loops
- 2) conditionals
- 3) goto
- 4) Proc. call
- 5) Proc. return

## Assembly



- |                               |                |
|-------------------------------|----------------|
| 1) byte                       | 3) branch/jump |
| 2) 4-byte long word           | 4) call        |
| 3) 8-byte quad word           | 5) ret         |
| 4) contiguous byte allocation |                |
| 5) address of initial byte    |                |

# Pentium Pro (P6)


## History

- **Announced in Feb. '95**
- **Basis for Pentium II, Pentium III, Pentium 4, and Celeron processors**

## Features

- **Dynamically translates instructions to more regular format**
  - Very wide, but simple instructions
- **Executes operations in parallel**
  - Up to 5 at once
- **Very deep pipeline**
  - 12–18 cycle latency

# PentiumPro Block Diagram



Microprocessor Report  
2/16/95

# PentiumPro Operation

**Translates instructions dynamically into “Uops”**

- 118 bits wide
- Holds operation, two sources, and destination

**Executes Uops with “Out of Order” engine**

- Uop executed when
  - Operands available
  - Functional unit available
- Execution controlled by “Reservation Stations”
  - Keeps track of data dependencies between uops
  - Allocates resources

**Consequences**

- Indirect relationship between IA32 code & what actually gets executed
- Difficult to predict / optimize performance at assembly level

# Whose Assembler?

## Intel/Microsoft Format

```
lea    eax,[ecx+ecx*2]
sub     esp,8
cmp     dword ptr [ebp-8],0
mov     eax,dword ptr [eax*4+100h]
```

## GAS/Gnu Format

```
leal    (%ecx,%ecx,2),%eax
subl    $8,%esp
cmpl    $0,-8(%ebp)
movl    $0x100(,%eax,4),%eax
```

## Intel/Microsoft Differs from GAS

- Operands listed in opposite order

mov Dest, Src

movl Src, Dest

- Constants not preceded by '\$', Denote hexadecimal with 'h' at end

100h

\$0x100

- Operand size indicated by operands rather than operator suffix

sub

subl

- Addressing format shows effective address computation

[eax\*4+100h]

\$0x100(,%eax,4)