## **Floating Point**

15-213/18-243: Introduction to Computer Systems 4<sup>th</sup> Lecture, 30 May 2012

#### **Instructors:**

**Gregory Kesden** 

## **Last Time: Integers**

- Representation: unsigned and signed
- Conversion, casting
  - Bit representation maintained but reinterpreted
- Expanding, truncating
  - Truncating = mod
- Addition, negation, multiplication, shifting
  - Operations are mod 2<sup>w</sup>
  - Pay attention to division of negative numbers
- "Ring" properties hold
  - Associative, commutative, distributive, additive 0 and inverse
- Ordering properties do not hold
  - u > 0 does not mean u + v > v
  - u, v > 0 does not mean  $u \cdot v > 0$


# **Today: Floating Point**

- Background: Fractional binary numbers
- IEEE floating point standard: Definition
- Example and properties
- Rounding, addition, multiplication
- Floating point in C
- Summary

# **Fractional binary numbers**

■ What is 1011.101<sub>2</sub>?

# **Fractional Binary Numbers**



- Bits to right of "binary point" represent fractional powers of 2
- Represents rational number:

$$\sum_{=-i}^{i} b_k imes 2^k$$

# **Fractional Binary Numbers: Examples**

#### Value Representation

5 3/4 101.11<sub>2</sub>
2 7/8 10.111<sub>2</sub>
63/64 1.0111<sub>2</sub>

#### Observations

- Divide by 2 by shifting right
- Multiply by 2 by shifting left
- Numbers of form 0.111111...2 are just below 1.0
  - $1/2 + 1/4 + 1/8 + ... + 1/2^i + ... \rightarrow 1.0$
  - Use notation 1.0 ε

### **Representable Numbers**

#### Limitation

- Can only exactly represent numbers of the form x/2<sup>k</sup>
- Other rational numbers have repeating bit representations

#### Value Representation

- **1/3** 0.01010101[01]...<sub>2</sub>
- **1/5** 0.00110011[0011]...2
- **1/10** 0.0001100110011[0011]...<sub>2</sub>

## **Today: Floating Point**

- Background: Fractional binary numbers
- IEEE floating point standard: Definition
- **■** Example and properties
- Rounding, addition, multiplication
- Floating point in C
- Summary

### **IEEE Floating Point**

#### IEEE Standard 754

- Established in 1985 as uniform standard for floating point arithmetic
  - Before that, many idiosyncratic formats
- Supported by all major CPUs

### Driven by numerical concerns

- Nice standards for rounding, overflow, underflow
- Hard to make fast in hardware
  - Numerical analysts predominated over hardware designers in defining standard

## **Floating Point Representation**

#### Numerical Form:

$$(-1)^{s} M 2^{E}$$

- Sign bit s determines whether number is negative or positive
- **Significand M** normally a fractional value in range [1.0,2.0).
- **Exponent** *E* weights value by power of two


#### Encoding

- MSB s is sign bit s
- exp field encodes *E* (but is not equal to E)
- frac field encodes M (but is not equal to M)


s	exp	frac
---	-----	------

### **Precisions**


■ Single precision: 32 bits



■ Double precision: 64 bits



Extended precision: 80 bits (Intel only)



### **Normalized Values**

- Condition: exp ≠ 000...0 and exp ≠ 111...1
- Exponent coded as *biased* value: E = Exp Bias
  - Exp: unsigned value exp
  - $Bias = 2^{k-1} 1$ , where k is number of exponent bits
    - Single precision: 127 (Exp: 1...254, E: -126...127)
    - Double precision: 1023 (Exp: 1...2046, E: -1022...1023)
- Significand coded with implied leading 1:  $M = 1.xxx...x_2$ 
  - xxx...x: bits of frac
  - Minimum when 000...0 (M = 1.0)
  - Maximum when 111...1 ( $M = 2.0 \varepsilon$ )
  - Get extra leading bit for "free"

### Normalized Encoding Example

```
■ Value: Float F = 15213.0;
```

```
■ 15213_{10} = 11101101101101_2
= 1.1101101101101_2 x 2^{13}
```

#### Significand

```
M = 1.101101101_2
frac= 101101101101_000000000_2
```

#### Exponent

```
E = 13
Bias = 127
Exp = 140 = 10001100_{2}
```

#### Result:

0 10001100 1101101101101000000000

s exp frac


### **Denormalized Values**

- **Condition:** exp = 000...0
- **Exponent value:** E = 1 Bias (instead of E = Bias)
- Significand coded with implied leading 0: *M* = 0.xxx...x<sub>2</sub>
  - xxx...x: bits of frac
- Cases
  - exp = 000...0, frac = 000...0
    - Represents zero value
    - Note distinct values: +0 and -0 (why?)
  - exp = 000...0,  $frac \neq 000...0$ 
    - Numbers very close to 0.0
    - Lose precision as get smaller
    - Equispaced

## **Special Values**

- **Condition: exp** = 111...1
- **Case:** exp = 111...1, frac = 000...0
  - Represents value ∞ (infinity)
  - Operation that overflows
  - Both positive and negative
  - E.g.,  $1.0/0.0 = -1.0/-0.0 = +\infty$ ,  $1.0/-0.0 = -\infty$
- Case: exp = 111...1,  $frac \neq 000...0$ 
  - Not-a-Number (NaN)
  - Represents case when no numeric value can be determined
  - E.g., sqrt(-1),  $\infty \infty$ ,  $\infty \times 0$


# Visualization: Floating Point Encodings



## **Today: Floating Point**

- Background: Fractional binary numbers
- IEEE floating point standard: Definition
- Example and properties
- Rounding, addition, multiplication
- Floating point in C
- Summary

# **Tiny Floating Point Example**



#### 8-bit Floating Point Representation

- the sign bit is in the most significant bit
- the next four bits are the exponent, with a bias of 7
- the last three bits are the frac

#### Same general form as IEEE Format

- normalized, denormalized
- representation of 0, NaN, infinity


# **Dynamic Range (Positive Only)**

	s	ехр	frac	E	Value
	0	0000	000	-6	0
	0	0000	001	-6	1/8*1/64 = 1/512 closest to zero
Denormalized	0	0000	010	-6	2/8*1/64 = 2/512
numbers	•••				
	0	0000	110	-6	6/8*1/64 = 6/512
	0	0000	111	-6	7/8*1/64 = 7/512 largest denorm
	0	0001	000	-6	8/8*1/64 = 8/512 smallest norm
	0	0001	001	-6	9/8*1/64 = 9/512
	•••				
	0	0110	110	-1	14/8*1/2 = 14/16
	0	0110	111	-1	15/8*1/2 = 15/16 closest to 1 below
Normalized	0	0111	000	0	8/8*1 = 1
numbers	0	0111	001	0	9/8*1 = 9/8 closest to 1 above
	0	0111	010	0	10/8*1 = 10/8
	•••				
	0	1110	110	7	14/8*128 = 224
	0	1110	111	7	15/8*128 = 240   largest norm
	0	1111	000	n/a	inf


### **Distribution of Values**

#### 6-bit IEEE-like format

- e = 3 exponent bits
- f = 2 fraction bits
- Bias is 23-1-1 = 3




Notice how the distribution gets denser toward zero.




# Distribution of Values (close-up view)

#### 6-bit IEEE-like format

- e = 3 exponent bits
- f = 2 fraction bits
- Bias is 3





### **Interesting Numbers**

■ Single  $\approx 3.4 \times 10^{38}$ 

■ Double  $\approx 1.8 \times 10^{308}$ 

{single,double}

Description	exp	frac	Numeric Value
Zero	0000	0000	0.0
Smallest Pos. Denorm.	0000	0001	$2^{-\{23,52\}} \times 2^{-\{126,1022\}}$
■ Single $\approx 1.4 \times 10^{-45}$			
■ Double $\approx 4.9 \times 10^{-324}$			
<ul><li>Largest Denormalized</li></ul>	0000	1111	$(1.0 - \varepsilon) \times 2^{-\{126,1022\}}$
■ Single $\approx 1.18 \times 10^{-38}$			
■ Double $\approx 2.2 \times 10^{-308}$			
Smallest Pos. Normalized	0001	0000	1.0 x $2^{-\{126,1022\}}$
Just larger than largest denor	nalized		
One	0111	0000	1.0
<ul><li>Largest Normalized</li></ul>	1110	1111	$(2.0 - \varepsilon) \times 2^{\{127,1023\}}$

# **Special Properties of Encoding**

- FP Zero Same as Integer Zero
  - All bits = 0

### ■ Can (Almost) Use Unsigned Integer Comparison

- Must first compare sign bits
- Must consider -0 = 0
- NaNs problematic
  - Will be greater than any other values
  - What should comparison yield?
- Otherwise OK
  - Denorm vs. normalized
  - Normalized vs. infinity

## **Today: Floating Point**

- Background: Fractional binary numbers
- IEEE floating point standard: Definition
- Example and properties
- Rounding, addition, multiplication
- Floating point in C
- Summary

# Floating Point Operations: Basic Idea

$$\mathbf{x} +_{\mathbf{f}} \mathbf{y} = \text{Round}(\mathbf{x} + \mathbf{y})$$

$$\mathbf{x} \times_{\mathbf{f}} \mathbf{y} = \text{Round}(\mathbf{x} \times \mathbf{y})$$

#### Basic idea

- First compute exact result
- Make it fit into desired precision
  - Possibly overflow if exponent too large
  - Possibly round to fit into frac

# Rounding

Rounding Modes (illustrate with \$ rounding)

	\$1.40	\$1.60	\$1.50	\$2.50	-\$1.50
<ul><li>Towards zero</li></ul>	\$1	\$1	\$1	\$2	<b>-</b> \$1
■ Round down (-∞)	\$1	\$1	\$1	\$2	<b>-</b> \$2
■ Round up $(+\infty)$	\$2	\$2	\$2	\$3	<b>-</b> \$1
<ul><li>Nearest Even (default)</li></ul>	\$1	\$2	\$2	\$2	<b>-</b> \$2

■ What are the advantages of the modes?

### **Closer Look at Round-To-Even**

#### Default Rounding Mode

- Hard to get any other kind without dropping into assembly
- All others are statistically biased
  - Sum of set of positive numbers will consistently be over- or underestimated

### Applying to Other Decimal Places / Bit Positions

- When exactly halfway between two possible values
  - Round so that least significant digit is even
- E.g., round to nearest hundredth

1.2349999	1.23	(Less than half way)
1.2350001	1.24	(Greater than half way)
1.2350000	1.24	(Half way—round up)
1 2450000	1 24	(Half way—round down)

### **Rounding Binary Numbers**

#### Binary Fractional Numbers

- "Even" when least significant bit is 0
- "Half way" when bits to right of rounding position = 100...2

#### Examples

Round to nearest 1/4 (2 bits right of binary point)

Value	Binary	Rounded	Action	Rounded Value
2 3/32	10.000112	10.002	(<1/2—down)	2
2 3/16	10.00 <mark>110</mark> 2	10.012	(>1/2—up)	2 1/4
2 7/8	10.11 <mark>100</mark> 2	11.002	( 1/2—up)	3
2 5/8	10.10 <mark>100</mark> 2	10.102	( 1/2—down)	2 1/2

# **FP Multiplication**

- $= (-1)^{s1} M1 2^{E1} \times (-1)^{s2} M2 2^{E2}$
- **Exact Result:**  $(-1)^s M 2^E$ 
  - Sign s: s1 ^ s2
  - Significand *M*: *M1* x *M2*
  - Exponent *E*: *E1 + E2*

#### Fixing


- If  $M \ge 2$ , shift M right, increment E
- If *E* out of range, overflow
- Round M to fit frac precision

#### Implementation

Biggest chore is multiplying significands

# **Floating Point Addition**

- - **A**ssume *E1* > *E2*
- Exact Result:  $(-1)^s M 2^E$ 
  - ■Sign *s*, significand *M*:
    - Result of signed align & add
  - ■Exponent *E*: *E*1



#### Fixing

- ■If  $M \ge 2$ , shift M right, increment E
- •if M < 1, shift M left k positions, decrement E by k
- ■Overflow if *E* out of range
- Round *M* to fit **frac** precision

# **Mathematical Properties of FP Add**

#### Compare to those of Abelian Group

Closed under addition?
Yes

But may generate infinity or NaN

Commutative?

Associative?

Overflow and inexactness of rounding

• 0 is additive identity?

Every element has additive inverse Almost

Except for infinities & NaNs

#### Monotonicity

■  $a \ge b \Rightarrow a+c \ge b+c$ ? **Almost** 

Except for infinities & NaNs

# **Mathematical Properties of FP Mult**

### Compare to Commutative Ring

Closed under multiplication?
Yes

But may generate infinity or NaN

Multiplication Commutative?

• Multiplication is Associative?

Possibility of overflow, inexactness of rounding

1 is multiplicative identity?

• Multiplication distributes over addition?

Possibility of overflow, inexactness of rounding

#### Monotonicity

•  $a \ge b \ \& c \ge 0 \Rightarrow a * c \ge b * c$ ?

**Almost** 

Except for infinities & NaNs

# **Today: Floating Point**

- Background: Fractional binary numbers
- IEEE floating point standard: Definition
- **■** Example and properties
- Rounding, addition, multiplication
- Floating point in C
- Summary

# **Floating Point in C**

#### C Guarantees Two Levels

- •float single precision
- **double** double precision


### Conversions/Casting

- Casting between int, float, and double changes bit representation
- double/float → int
  - Truncates fractional part
  - Like rounding toward zero
  - Not defined when out of range or NaN: Generally sets to TMin
- int → double
  - Exact conversion, as long as int has ≤ 53 bit word size
- int → float
  - Will round according to rounding mode

### **Creating Floating Point Number**

#### Steps

- Normalize to have leading 1
- Round to fit within fraction



Postnormalize to deal with effects of rounding


### Case Study

Convert 8-bit unsigned numbers to tiny floating point format

#### **Example Numbers**

128	10000000
13	00001101
17	00010001
19	00010011
138	10001010
63	00111111

### **Normalize**



### Requirement

- Set binary point so that numbers of form 1.xxxxx
- Adjust all to have leading one
  - Decrement exponent as shift left

Value	Binary	Fraction	Exponent
128	10000000	1.0000000	7
13	00001101	1.1010000	3
17	00010001	1.0001000	4
19	00010011	1.0011000	4
138	10001010	1.0001010	7
63	00111111	1.1111100	5

# Rounding

#### Binary Fractional Numbers

- "Even" when least significant bit is 0
- "Half way" when bits to right of rounding position = 100...2

Value	Fraction	Incr?	Rounded
128	1.0000000	N	1.000
15	1.1010000	N	1.101
17	1.000 <mark>1000</mark>	N	1.000
19	1.001 <mark>1000</mark>	Υ	1.010
138	1.000 <mark>1010</mark>	Υ	1.001
63	1.111 <mark>1100</mark>	Υ	10.000

### **Postnormalize**

#### Issue

- Rounding may have caused overflow
- Handle by shifting right once & incrementing exponent

Value	Rounded	Exp	Adjusted	Resul	lt float_8
128	1.000	7		128	01110000
13	1.101	3		13	01010101
17	1.000	4		16	01011000
19	1.010	4		20	01011010
138	1.001	7		144	01110001
63	10.000	5	1.000/6	64	01101000

Remember that E = e - biasBias = 7

## **Floating Point Puzzles**

#### ■ For each of the following C expressions, either:

- Argue that it is true for all argument values
- Explain why not true

```
int x = ...;
float f = ...;
double d = ...;
```

Assume neither **d** nor **f** is NaN

```
• x == (int)(float) x
```

• 
$$x == (int)(double) x$$

• 
$$f == -(-f);$$

• 
$$2/3 == 2/3.0$$

• 
$$d < 0.0$$
  $\Rightarrow$   $((d*2) < 0.0)$ 

• 
$$d > f$$
  $\Rightarrow$   $-f > -d$ 

• 
$$d * d >= 0.0$$

• 
$$(d+f)-d == f$$

### **Today: Floating Point**

- Background: Fractional binary numbers
- **IEEE floating point standard: Definition**
- Example and properties
- Rounding, addition, multiplication
- Floating point in C
- Summary

### **Summary**

- IEEE Floating Point has clear mathematical properties
- Represents numbers of form M x 2<sup>E</sup>
- One can reason about operations independent of implementation
  - As if computed with perfect precision and then rounded
- Not the same as real arithmetic
  - Violates associativity/distributivity
  - Makes life difficult for compilers & serious numerical applications programmers